


# How to run the project in Netbeans IDE

1. Download code from Github (<https://github.com/inertiaelements/OsmiumScope-Java>).


The screenshot shows the GitHub repository page for `inertiaelements/OsmiumScope-Java`. The repository has 4 commits, 1 branch, 0 releases, and 1 contributor. The 'Clone or download' dropdown menu is open, showing the 'Download ZIP' button circled in green. The repository description is 'OsmiumScope - Data Logging & Analysis tool' with a link to <https://inertiaelements.com>. The file list includes `data`, `images`, `lib`, `nbproject`, `src`, and `CONTRIB.md`. The 'Download ZIP' button is highlighted with a green circle.

File/Folder	Action	Time
<code>data</code>	Add files via upload	11 hours ago
<code>images</code>	Add files via upload	11 hours ago
<code>lib</code>	Add files via upload	11 hours ago
<code>nbproject</code>	Add files via upload	11 hours ago
<code>src</code>	Add files via upload	11 hours ago
<code>CONTRIB.md</code>	Add files via upload	11 hours ago


2. Unzip the OsmiumScope-Java-master.zip (e.g. “C:\Users\admin\Downloads\OsmiumScope-Java-master.zip”).



3. Open the Netbeans IDE and click on File -> Open Project.



4. Browse to unzip folder “C:\Users\admin\Downloads\OsmiumScope-Java-master” folder.



5. Connect your device (MIMU22BL) using USB cable.

6. To find the serial port's name, refer this link <https://www.inertiaelements.com/oblu/resources/how-to-find-serial-port.pdf>

7. Open **config.properties** and change the value of parameter **com.rotate.serialport** as you get in Step # 6. You change the data sampling frequency by changing the value of **com.rotate.outrate** but its value must be one of following:


250

125

62.5

31.25

15.625



8. Now run the project. Right click on “**OsmiumScope-Java**” project and select **Run**.

